

COMSOL LEP tutorial for Tank flow system (Two CSTR in series)

Step 1: Open chapter 13 and click on **COMSOL** tab present in the bottom of the page

The screenshot shows the website interface for 'Elements of Chemical Reaction Engineering, 5th Edition'. The top navigation bar includes 'Home', 'Problem Solving Updates and FAQs', and 'COMSOL' (circled in red). The main content area is titled 'Chapter 13: Unsteady State Nonisothermal Reactor Design' and lists 'Objectives' for the chapter. Below the objectives, there are several resource tabs: 'Learning Resources', 'Living Example Problems', 'Expanded Material', 'Youtube Videos', 'Professional Reference Shelf', 'Additional Homework Problems', 'Web Modules', and 'COMSOL' (circled in red). A 'Self test' section includes 'A. Exercises' and 'B. >clicker questions'.

Step 2: The following page will open. Click on “How to access COMSOL”

The screenshot shows the website interface for 'Elements of Chemical Reaction Engineering, 5th Edition'. The top navigation bar includes 'Home', 'Problem Solving Updates and FAQs', and 'COMSOL' (circled in red). The main content area is titled 'How to access COMSOL' and contains a link to the 'COMSOL LEP tutorial'.

Step 3: The following page will open. Click “Here”

Elements of Chemical Reaction Engineering 5th Edition

Home
Problem Solving
Updates and FAQs

Essentials of Chemical Reaction Engineering

TOC 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 Appendices

BY CHAPTER HIDE

- Objectives
- Learning Resources -Summary Notes
- Living Example Problems
- Professional Reference Shelf
- Additional HW Problems
- FAQs
- Expanded Material

Please visit [HERE](#) to access COMSOL.

- If you are a student at the University of Michigan, please use your unique-name and password.
- If you are not a University of Michigan student, use
username: guest
password: guest

Step 4: This will take you to COMSOL Server. If you are a student at the University of Michigan, please use your Uniqname and password. If you are not a University of Michigan student, use

username: guest
password : guest


COMSOL
SERVER™

Username
guest


Password
.....

Log in to COMSOL Server


Step 5: This will open up COMSOL library where you see many COMSOL files to solve chemical reaction engineering problems. Find “Ideal Stirred Tank Reactor System”. Click on “Run in browser” to start the application



You will see that following window opens which has input parameters, description, graphical features and a few buttons. You can see the concentration profile on the right side of the page




Step 6: Click on Tank Volume tab to view the volume of each tank with time




Step 7: Under Input section on the left hand side, you can view and change any parameter values. Let's change a parameter and see the effect on the profile. Change the Inlet concentration in tank 1 from 1000 mol/m³ to 1500 mol/m³. After you are done, click on Compute button (=) present above the Input parameters


Caution: The y axis is dynamic and scale changes with respect to the values. Make sure to look at both scale and graph




Step 8: Now check the Concentration profile. The following graph will be obtained which shows that concentration of both the species has increased in both the tanks




Check the Tank volume profile. It can be seen that there is negligible effect on Tank volume




Step 9: Now if you want to re-set all the parameter values to its initial values, click on “reset to default button(↶). Click on this button and you will find that it resets the value of Inlet concentration. To update the graph, click on Compute button. Each time you change a variable, click Compute




Step 10: Now consider a case where you need to decrease concentration of A at the outlet of Tank 2 in the given time by changing reactor volume. Let's increase the Initial volume of Tank, 2 from 1.5 m³ to 20 m³ and click compute to update the results.



The following graph will be obtained for Concentration profile. You can check that concentration of A in tank 2 has decreased




The following graph will be obtained for Reactor tank volumes at different times




Step 11: Now, you can change any listed parameter value and check its effect on profiles. Make sure to click Compute button after you change a variable.

Step 12: If you have COMSOL installed on your computer, then you can also download the complete COMSOL file (with user interface)

- Go to file on toolbar and click on Save button. This will download the file at the bottom of the browser (if you are using Chrome)
- Click on the downloaded file to open the application



Step 13: You can also open a pdf documentation which details the reactor model and a step-by-step procedure to create this COMSOL module from scratch. Click on PDF button present on the menu bar



This will open up a new tab with PDF file which you can also download

